

Hammoude Software's Instructions

This document presents the main instructions to use the *Hammoude* software.

- Exit: The present window is closed and the software ends.

- New Project: A new window is opened to indicate the directory and project name. The directory should be select using the right button (represented by ...), and the name of the project should be directly written in the textbox. After entering the appropriate data and clicking “OK”, the “*Metric*” screen window appears.

- Metric: Firstly, the user needs to indicate the four parameters of the base image: scale (s), classes (t), unit parcel size (u) and repetition (r). The minimum and maximum values are 1 and 10 for all parameters. In the end, it is necessary indicate the location of the segmented image to use. The location should be select using the right button (represented by ...). None of the parameters present in this window can be left void. When the process is finished the software ends, and four text files are saved in the directory initially defined.